



Mobile APN Settings

Android

1. Open the Settings app.
2. Select Wireless & Networks > Mobile Networks > Access Point Names.
3. Click the Menu button.
4. Select **New APN**.
5. Enter **yourmobile** into the APN field.
Important: Make sure there's NO space before or after yourmobile
6. Click the Menu button.
7. Select Save.

BlackBerry

1. Select Settings > Options.
2. Complete one of the following:
 - BlackBerry v4.0 or earlier, click TCP/IP.
 - BlackBerry v4.1 to 5.0, click Advanced Options > TCP/IP.
 - BlackBerry v6.0 and later, click Device > Advanced System Settings > TCP/IP.
3. Enter **yourmobile** into the APN field.
Important: Make sure there's NO space before or after yourmobile
4. Press the Menu key.
5. Select Save.

iOS - iPad (iOS 6/7)

1. Click on the Settings icon.
2. In the settings menu select **Cellular Data**.
3. Select **APN Settings**.
4. Enter **yourmobile** into the APN field.
Important: Make sure there's NO space before or after yourmobile



iOS - iPhone (iOS 7+)

1. Click on the Settings icon.
2. In the settings menu select Mobile.
3. Select Mobile Data Network.
4. Under the **Mobile Data** grouping, enter **yourmobile** into the APN field.
*Important: Make sure there's NO space before or after **yourmobile***

iOS - iPhone (iOS 6-)

1. Click on the Settings icon.
2. In the settings menu select General.
3. Select Cellular or Mobile.
4. Under the **Cellular Data Network** grouping, enter **yourmobile** into the APN field.
*Important: Make sure there's NO space before or after **yourmobile***

Symbian

1. Select Menu > Settings > Configurations.
2. Select Personal Configuration Settings > Add.
3. Select Access Point Settings > Bearer Settings.
4. Enter **yourmobile** into the APN field.
*Important: Make sure there's NO space before or after **yourmobile***
5. Go back to **Personal Configuration Settings** menu.
6. Select **yourmobile**
7. Click Options and choose Activate.



Windows Phone

1. In the App list, select the Settings icon.
2. Select Cellular.
3. Select **Add Internet APN**.
4. Enter **yourmobile** into the APN field
*Important: Make sure there's NO space before or after **yourmobile**.*
5. Select Save.